

Android 9



Exchange mailbox Android 9 Exchange on Fairphone

For use by:	Students, Employees
Version:	1.0
Date:	04-05-2020
Owner:	SID-LIB /ICT


Adding your Exchange mailbox to Android 9

Before you begin


The following instructions are supported by TU Delft and have been tested to be working. We are offering this manual to you as an extra service. In the event you have a different configuration or version of Android than 9 or lower or a different type of phone than Fairphone, and you have problems connecting, we advise you to contact your nearest Service Desk, Student IT Desk (SID) or Workplace services (WPS).

Connecting your Android 9 Fairphone to your personal mailbox


Step 1. Go to the **Settings** app and tap **Accounts**.




Step 2. Tap on **Add account**.



Step 3. Tap on **Exchange**.



Step 4. Enter your **e-mail address** and tap **Set up manually**.



Step 5. Your e-mail address will be filled in automatically. Fill in the following settings:

- Enter your **NetID password**
- Enter Domain\username: **Dastud\yournetid**
- Enter server: **webmail.tudelft.nl**

Tap **Next**.

13:47

ACCOUNT INFO

Email
your.email.address@tudelft.nl

Password
.....

Client certificate
None [SELECT](#)

SERVER SETTINGS


Domain\Username
dastud\netid

Server
webmail.tudelft.nl

[Next](#)

Step 6. Tap **Review permissions**.

13:48



Gmail needs access to this phone

Your IT admin needs Gmail to access this phone. You'll need to review and approve permissions on the next screen.

[Review permissions](#)

Step 7. Scroll down and tap **Activate this device admin app**.

13:48

Activate device admin app?

Set password rules
Control the length and the characters allowed in screen lock passwords and PINs.

Monitor screen unlock attempts
Monitor the number of incorrect passwords typed, when unlocking the screen, and lock the phone or erase all the phone's data if too many incorrect passwords are typed.

Lock the screen
Control how and when the screen locks.

Set screen lock password expiration
Change how frequently the screen lock password, PIN, or pattern must be changed.

Set storage encryption
Require that stored app data be encrypted.

Disable cameras
Prevent use of all device cameras.


Disable some screen lock features
Prevent use of some screen lock features.

[Activate this device admin app](#)

[Cancel](#)

Step 8. Your e-mail, contacts and calendar will now be synced. This may take some time.

13:49



Your account is ready to go!



[Done](#)